



STORMSHIELD



GUIDE

STORMSHIELD LOG SUPERVISOR

UPDATE GUIDE

Versions 1 and 2

Document last updated: July 4, 2024

Reference: sls-en_update_gde



Table of contents

Change log	3
Getting started	4
Patch dependencies	5
Downloading an SLS patch	6
Updating SLS	7
From version 1.1.1 to 2.0.0	7
Specific patch installation requirements	7
Install the SLS Upgrade Helper	7
Install the SLS version 2.0.0 patch	8
From version 1.1.0 to 1.1.1	10
From version 1.0.0 to 1.1.0	12
Further reading	13
Appendix: Extending disk size with an added disk	14



Change log

Date	Description
July 4, 2024	New document



Getting started

Welcome to the SLS Update Guide.

To update your SLS to a newer version, we recommend that you carefully follow this guide.

Before updating SLS, be sure to:

- Read the following documents:
 - The [Product life cycle Log Supervisor](#) guide.
SLS versions are divided into major, minor and corrective versions. For more information about the SLS Life Cycle management policy and SLS compatibilities, refer to this guide. If a version has several patch versions, always choose the most recent so that you benefit from the latest functional patches and bug fixes.
 - The [SLS Release Notes](#) to find out what the SLS versions contain.
- Back up SLS by creating a snapshot of the virtual machine so that you can restore it if necessary.

In this document, Stormshield Log Supervisor is referred to in its short form SLS.

NOTE

This document covers the update of an existing SLS. Specific [deployment guides](#) are available for a new SLS installation.



Patch dependencies

To update SLS, you need the update file (.pak) of the corresponding version. In SLS, an update file is called a patch.


Depending on your current SLS version, you may need to install one or more intermediate patches:

Version / Patch	Can be installed on
2.0.0	1.1.1
1.1.1	1.1.0
1.1.0	1.0.0


To determine which version of SLS is currently installed:

- For SLS version 1, click on the Stormshield Log Supervisor logo in the top banner,
- For SLS version 2, click on **Help > About SLS** in the navigation bar on the left.

SLS version 1



SLS version 2





Downloading an SLS patch

1. In your [MyStormshield](#) personal area, go to **Downloads** > **Downloads**.
2. Select **Stormshield Log Supervisor** from the suggested categories.
3. Download the SLS patch (.pak file) you want by clicking on its name. If you need to install multiple patches due to [patch dependencies](#), download them all now.
4. You can check the integrity of the downloaded file:
 1. Run one of the following commands:
 - Linux: `sha256sum <filename>`
 - Windows: `CertUtil -hashfile <filename> SHA256`
 2. Compare the result with the hash indicated in the MyStormshield interface. To view it, click on **Display** in the **SHA256** column of the file in question.



Updating SLS

Use the following procedures to update SLS to version **2.0.0**, **1.1.1** or **1.1.0**. Check the [patch dependencies](#) and be sure to apply all intermediate patches.

From version 1.1.1 to 2.0.0

! IMPORTANT
It is strongly recommended that you back up your SLS before starting this update procedure.

Specific patch installation requirements


- CPU: 8-core minimum
- RAM: 16GB minimum
- Minimum disk space required:
 - 500MB in */tmp*
 - 15GB in */opt*
 - 32GB in */opt/makalu/storage*

To check the available disk space, go to **Settings >> System Settings >> System Monitor** and click **Disk Usage**. If you need to increase the disk size, refer to the appendix [Extending disk size with an added disk](#).

Install the SLS Upgrade Helper


You must install the SLS Upgrade Helper version 1.0.0 **before** you upload the 2.0.0 patch. It changes the SLS patch installation path from */tmp* to */opt/immune/storage/tmp*.

1. Download the SLS Upgrade Helper file [*SLSUpgradeHelper_1.0.0.pak*] from your [MyStormshield](#) personal area in **Downloads > Downloads > Stormshield Log Supervisor**.
2. On SLS, go to **Configuration >> System >> Applications**.





3. Click **Import**.
4. Browse to the SLS Upgrade Helper *.pak* file and click **Upload**.




Install the SLS version 2.0.0 patch

NOTE


The process may take some time:

- Depending on your network connection, you may experience a longer patch upload time as the patch size is 6.4GB,
- Depending on system load and available resources, the patch will take between 30 and 60 minutes to install on the system.

1. Download the SLS version 2.0.0 patch from your [MyStormshield](#) personal area.
2. On SLS, go to **Settings >> System >> Updates**.



3. Click **Upload Patch**. Browse for the downloaded *.pak* file and click **Upload**.
4. Click the **Install Update** icon from the **Actions** column.





5. Allow 30 to 60 minutes to complete the update. You can refresh the **Updates** page at any time to see if the update is complete. When completed, the machine restarts and the *Status* of the SLS patch is *installed*.

If the installation fails with one of the following error messages:

```
Precondition fail - /opt should have at least 7.0GB of free space
```


```
Precondition fail - /opt/makalu/storage should have at least 25GB of free space
```

You must increase the disk size. For more information, refer to the appendix [Extending disk size with an added disk](#).




From version 1.1.0 to 1.1.1

1. Download the SLS version 1.1.1 patch from your [MyStormshield](#) personal area.
2. On SLS, go to **Settings >> System >> Updates**.



3. Click **Upload Patch**. Browse for the downloaded *.pak* file and click **Upload**. Please wait a few minutes as the file may take some time to upload.
4. Click the **Install Update** icon from the **Actions** column.




5. Wait a few moments for the update to end. Note that the **Install Logs** window does not notify you when the installation is complete. Go back to the **Updates** page to check that the *Status* of the SLS patch is *installed*.
6. To access the new version of SLS, log out from the user interface and then log in.

If you were using SNS built-in dashboards without any customization, you must manually remove the old dashboards and add the new ones:


1. Go to **Dashboard** from the navigation menu.
2. Remove all SNS dashboards by clicking the **Remove Dashboard (X)** icon and clicking **Yes**.
3. Click the + icon to add the new dashboards and click **Vendor Dashboards**.



4. Select all **SNS** dashboards, and only SNS dashboards, then click **Ok**.



5. Select all **SNS** dashboards again, and click **Choose Repos**.
6. Unselect **Stormshield**, select **stormshield** (in lower case), then click **Done**.




7. Click **Ok** to add the new dashboards.
- You can now [update SLS to version 2.0.0](#).




From version 1.0.0 to 1.1.0

1. Download the SLS version 1.1.0 patch from your [MyStormshield](#) personal area.
2. On SLS, go to **Settings >> System >> Updates**.



3. Click **Upload Patch**. Browse for the downloaded *.pak* file and click **Upload**.
4. Click the **Install Update** icon from the **Actions** column.



5. Wait for the update to end. This takes several minutes. You can refresh the **Updates** page at any time to see if the update is complete. When completed, the machine restarts and the *Status* of the SLS patch is *installed*.
6. Refresh the page to access the new version of SLS.

You can now [update SLS to version 1.1.1](#).



Further reading

Additional information and answers to questions you may have about SLS are available in the [Stormshield knowledge base](#) (authentication required).



Appendix: Extending disk size with an added disk

This appendix explains how to extend your disk size. You may need to do this if your SLS patch update fails due to insufficient disk space.

! IMPORTANT

Effective management of disks and file systems is critical, as unintentional changes can result in data loss. Proceed at your own risk.

1. Log in to the SLS server CLI as a **li-admin** user.
2. Use the **lsblk** command to check the name of the newly added disk.

```
li-admin@LogPoint:~$ lsblk
NAME                                MAJ:MIN RM  SIZE RO  TYPE MOUNTPOINT
sda                                  8:0     0  100G  0  disk
├─sda1                               8:1     0   30M  0  part
├─sda2                               8:2     0   18G  0  part /
├─sda3                               8:3     0   7.5G  0  part [SWAP]
├─sda4                               8:4     0  74.6G  0  part
├─LogPoint--vg-app                   253:0   0  18.6G  0  lvm  /opt
├─LogPoint--vg-data                  253:1   0  55.9G  0  lvm  /opt/makalu/storage
sdb                                  8:16    0   10G  0  disk
```

Here, the new disk is **sdb**. Reboot the system if you can't see the new disk with the above command.

3. Check the size of the logical volume.

```
li-admin@LogPoint:~$ df -hT
Filesystem                Type      Size  Used Avail Use% Mounted on
udev                     devtmpfs  3.9G   0    3.9G   0% /dev
tmpfs                    tmpfs     797M 1000K 796M   1% /run
/dev/sda2                 ext4      18G   9.0G 7.8G  54% /
tmpfs                    tmpfs     3.9G   0    3.9G   0% /dev/shm
tmpfs                    tmpfs     5.0M   0    5.0M   0% /run/lock
tmpfs                    tmpfs     3.9G   0    3.9G   0% /sys/fs/cgroup
/dev/mapper/LogPoint--vg-app ext4       19G   2.8G 15G   17% /opt
/dev/mapper/LogPoint--vg-data ext4      55G  509M  52G   1% /opt/makalu/storage
tmpfs                    tmpfs     797M  4.0K 797M   1% /run/user/1000
```

The current size of **"/dev/mapper/LogPoint--vg-app"** is 19GB.

The current size of **"/dev/mapper/LogPoint--vg-data"** is 55GB.

4. Format the new disk and create a partition on it:
 1. Format the new disk with the **gdisk** command. (*gdisk /dev/sdb* in this case).
 2. Enter **n** to add a new partition.
 3. Enter **1** as the partition number.
 4. Choose **First sector**. Press **Enter** for default value.
 5. Choose **Last sector**. Press **Enter** for default value.
 6. Choose **Hex code 8e00** for Linux LVM.
 7. Then, press **p** to print new partition details.
 8. Press **w** to save the partition.
 9. Press **y** to confirm the partition creation.



```
li-admin@LogPoint:~$ gdisk /dev/sdb
GPT fdisk (gdisk) version 1.0.5

Partition table scan:
MBR: not present
BSD: not present
APM: not present
GPT: not present

Creating new GPT entries in memory.

Command (? for help): n
Partition number (1-128, default 1): 1
First sector (34-20971486, default = 2048) or {+-}size{KMGTP}:
Last sector (2048-20971486, default = 20971486) or {+-}size{KMGTP}:
Current type is 8300 (Linux filesystem)
Hex code or GUID (L to show codes, Enter = 8300): 8e00
Changed type of partition to 'Linux LVM'

Command (? for help): p
Disk /dev/sdb: 20971520 sectors, 10.0 GiB
Model: Virtual disk
Sector size (logical/physical): 512/512 bytes
Disk identifier (GUID): 0A72FB8E-D076-480C-85D1-9BD670641A55
Partition table holds up to 128 entries
Main partition table begins at sector 2 and ends at sector 33
First usable sector is 34, last usable sector is 20971486
Partitions will be aligned on 2048-sector boundaries
Total free space is 2014 sectors (1007.0 KiB)

Number  Start (sector)    End (sector)  Size      Code  Name
  1            2048             20971486     10.0 GiB   8E00   Linux LVM

Command (? for help): w

Final checks complete. About to write GPT data. THIS WILL OVERWRITE EXISTING
PARTITIONS!!

Do you want to proceed? (Y/N): y
OK; writing new GUID partition table (GPT) to /dev/sdb.
The operation has completed successfully.
```

5. Verify the newly created disk partition with **lsblk**.

```
li-admin@LogPoint:~$ lsblk
NAME                                MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
sda                                  8:0    0  100G  0 disk
├─sda1                               8:1    0   30M  0 part
├─sda2                               8:2    0   18G  0 part /
├─sda3                               8:3    0   7.5G  0 part [SWAP]
├─sd                                  8:4    0  74.6G  0 part
├─LogPoint--vg-app                   253:0  0  18.6G  0 lvm  /opt
├─LogPoint--vg-data                   253:1  0  55.9G  0 lvm  /opt/makalu/storage
sdb                                  8:16   0   10G  0 disk
└─sdb1                               8:17   0   10G  0 part
```

6. Create a new physical volume with the partition using **pvcreate /dev/sdb1**.

```
li-admin@logpoint:~$ pvcreate /dev/sdb1
Physical volume "/dev/sdb1" successfully created.
```

7. Extend the volume group first using **vgextend /dev/LogPoint-vg /dev/sdb1**. Running the **lsblk** command indicates that **LogPoint-vg** is the existing volume group and storage is the logical volume.

```
li-admin@logpoint:~$ vgextend /dev/LogPoint-vg /dev/sdb1
Volume group "LogPoint-vg" successfully extended
```



8. Extend the logical volume depending on your requirements.

- For **opt**, extend the logical volume *opt* using **lvextend /dev/LogPoint-vg/app /dev/sdb1**.

```
li-admin@LogPoint:~$ lvextend /dev/LogPoint-vg/app /dev/sdb1
Size of logical volume LogPoint-vg/app changed from 18.62 GiB (4768 extents) to
28.62 GiB (7327 extents).
Logical volume LogPoint-vg/app successfully resized.
```

- For **storage**, extend the logical volume *storage* using **lvextend /dev/LogPoint-vg/data /dev/sdb1**.

```
li-admin@LogPoint:~$ lvextend /dev/LogPoint-vg/data /dev/sdb1
Size of logical volume LogPoint-vg/data changed from 55.92 GiB (14316 extents) to
65.92 GiB (16875 extents).
Logical volume LogPoint-vg/data successfully resized.
```

9. Resize the logical volume.

- For **/opt**: **resize2fs /dev/LogPoint-vg/app**.

```
li-admin@LogPoint:~$ resize2fs /dev/LogPoint-vg/app
resize2fs 1.45.5 (07-Jan-2020)
Filesystem at /dev/LogPoint-vg/app is mounted on /opt; on-line resizing required
old_desc_blocks = 2, new_desc_blocks = 2
The filesystem on /dev/LogPoint-vg/app is now 7502848 (4k) blocks long.
```

- For **storage**: **resize2fs /dev/LogPoint-vg/data**.

```
li-admin@LogPoint:~$ resize2fs /dev/LogPoint-vg/data
resize2fs 1.45.5 (07-Jan-2020)
Filesystem at /dev/LogPoint-vg/data is mounted on /opt/makalu/storage; on-line
resizing required
old_desc_blocks = 4, new_desc_blocks = 5
The filesystem on /dev/LogPoint-vg/data is now 17280000 (4k) blocks long.
```

10. Verify the increased disk size using **lsblk**.

```
li-admin@LogPoint:~$ lsblk
NAME                                MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
sda                                  8:0    0  100G  0 disk
├─sda1                               8:1    0   30M  0 part
├─sda2                               8:2    0   18G  0 part /
├─sda3                               8:3    0   7.5G  0 part [SWAP]
└─sda4                               8:4    0  74.6G  0 part
├─LogPoint--vg-app                 253:0    0  18.6G  0 lvm  /opt
└─LogPoint--vg-data                253:1    0  65.9G  0 lvm  /opt/makalu/storage
sdb                                  8:16    0   10G  0 disk
├─sdb1                             8:17    0   10G  0 part
└─LogPoint--vg-data                253:1    0  65.9G  0 lvm  /opt/makalu/storage
```




STORMSHIELD

documentation@stormshield.eu

All images in this document are for representational purposes only, actual products may differ.

Copyright © Stormshield 2024. All rights reserved. All other company and product names contained in this document are trademarks or registered trademarks of their respective companies.